



INTEGRATION GUIDE

How to Configure Aerohive Wi-Fi Cloud to Secure your Wireless Network with Portnox CLEAR

Introduction

This document guides you step by step how to configure your Aerohive wireless cloud environment using Portnox CLEAR to ensure secure and trusted user access.

Enabling CLEAR RADIUS Service

The first step is to enable the CLEAR RADIUS service:

- 1) Verify your organization is registered on Portnox CLEAR Cloud Services: https://clear.portnox.com/.
- 2) In the CLEAR portal, go to **Settings** > **Services** and expand **CLEAR RADIUS Service**. Then:
 - a. If the **Enable Cloud RADIUS** checkbox is not checked, click **Edit** and check the **Enable Cloud RADIUS** checkbox.
 - b. Note the RADIUS server details which you will need when configuring the Aerohive Controller:
 - Cloud RADIUS IP this is the IP address of the CLEAR RADIUS server
 - Authentication port
 - Accounting port needed for the RADIUS accounting server
 - Shared Secret this is the RADIUS client shared secret

Registering the SSID in CLEAR

The second step is to register, in the CLEAR portal, the SSID of the wireless network you will be securing.

- 1) Navigate in the portal to **Settings** > **Groups**.
- 2) Edit the default "Unassigned" group or create a new security group.
- 3) Whether you are creating or editing a group, in **Group Settings** click **Add Wi-Fi network** and specify the **SSID** of the network you will be securing.

Configuring the Aerohive Wi-Fi SSID

In the final step, we configure the Aerohive wireless SSID to be secured and protected based on CLEAR RADIUS authentication.

- In the Aerohive Hive Manager portal, navigate to Configure > Add Network Policy, and add a new network policy or edit an existing one.
- 2) Navigate to Configure > Wireless Networks and add new SSID > All other Networks (standard).
- 3) In the Wireless Networks tab, do the following:
 - a. Specify Name (SSID).
 - b. Select Enterprise WPS / WPA2 802.1X as SSID authentication.
 - c. Select WPA-(WPA2 Enterprise)-802.1X as the Key Management.
 - d. Select AES or TKIP as an Encryption Method.

AEROHIVE. DASHBOAI	RD MONITOR MAPS	CONFIGURE TOOLS	A3			
NETWO	ORK POLICIES APPLICATIONS	COMMON OBJECTS USERS	1			
Network Policies > CLEAR > All SS	SIDs 2 New SSID					
Policy Details		Wireless Networks	Device Te	mplates	Router Settings	
CONFIGURATION GUIDE	Wireless Network	x				
Policy Name	Nome (SSID) #		Broad	cast SSID Using		
CLEAR	Name (SSID)	CLEAR	🔽 v	ViFi0 Radio (2.4 GHz	or 5 GHz)	
SSID (Name)	Broadcast Name *	CLEAR	v v	ViFi1 Radio (5 GHz o	nly)	
CLEAR RADIUS Server Group		3				
+ Add Radius Server Group	CCID Lloggo					
	SSID Usage					
	SSID Authenticatio	MAC Authentication				
	020 Enterprise	ĸ	O Personal WPA/WPA2 PSK		မို့ Private Pre-Shared Key	
	Key Management	WPA2-(WPA2	Enterprise)-802.1X 🔹			
	Encryption Method	CCMP (AES)	*			

e. In **the Authentication settings > Authenticate via Radius server > press "+"** to add new Radius server.

f. Specify RADIUS Server Group Name and press "+" to add new External Radius Server.

Enter the following CLEAR RADIUS server details, which you noted in <u>Enabling CLEAR RADIUS</u> <u>Service</u>, step (2)b:

- In **IP/Host Name**, enter the Cloud RADIUS IP.
- In **Server Type > Authentication Port**, enter the Authentication port number.
- In **Server Type > Accounting Port**, enter the Accounting port number.
- In **Shared Secret**, enter the Shared Secret.
- g. Press Save External Radius Server.

Configure RADIUS Server	S				×
RADIUS Server Group Name *	RADIUS Server Gr	oup Description			
CLEAR-GROUP		*			
EXTERNAL RADIUS SERVER (0)	AEROHIVE A3 (0)	AEROHIVE RADIUS SERVER (0)	AEROHIVE RADIUS PROXY (0)	LOCAL DATABASE (0)	[i] +
New External RADIUS Se	rver				
Name *	CLEAR-RADIU	S			
Description					
IP/Host Name *		· ا			
Server Type *	Authentication	Port: *			
	Accounting	Port: *			
Shared Secret					
	Show Passwo	rd			



h. Select the Radius server and press **Save Radius**.

Configure RADIUS Server	s				×
RADIUS Server Group Name *	RADIUS Server Gro	up Description			
CLEAR-GROUP		<i>b</i>			
EXTERNAL RADIUS SERVER (1)	AEROHIVE A3 (0)	AEROHIVE RADIUS SERVER (0)	AEROHIVE RADIUS PROXY (0)	LOCAL DATABASE (0)	Ci +
Name		IP	/Host Name		
			8		
			-		
CLEAR-RADIUS					
				CANCEL	SAVE RADIUS
Authentication Settings					
Authentication with HiveManage	r Authentication Ser	rvice OFF			
Authenticate via RAD	US Server				
Default RADIUS Server Group CLEAR-G	ROUP	F 5≓			
Name		Туре			IP/Host Nam
CLEAR-RADIUS		External RAI	DIUS Server		

i. Select the relevant SSID and press next, add new AP template and press next.

AP Templates	Switch Templates		
AP Templates			
ADD 📻 🛅			
Device Model	Template	Classification Rules	Assignment Description
AP130	Temp-AP (default)		

j. In order to apply the network policy to selected devices > **upload**.

Apply the network policy to selected devices

Status	Device Name	Device Model	IP Address	MAC Address
•	AH-641c00	AP130		